
Summarizing Measured Data

Raj Jain Washington University in Saint Louis Saint Louis, MO 63130 Jain@cse.wustl.edu

These slides are available on-line at:

http://www.cse.wustl.edu/~jain/cse567-08/



Part III: Probability Theory and Statistics


- 1. How to report the performance as a single number? Is specifying the mean the correct way?
- 2. How to report the variability of measured quantities? What are the alternatives to variance and when are they appropriate?
- 3. How to interpret the variability? How much confidence can you put on data with a large variability?
- 4. How many measurements are required to get a desired level of statistical confidence?
- 5. How to summarize the results of several different workloads on a single computer system?
- 6. How to compare two or more computer systems using several different workloads? Is comparing the mean sufficient?
- 7. What model best describes the relationship between two variables? Also, how good is the model?

Washington University in St. Louis

CSE567M

Basic Probability and Statistics Concepts

- Independent Events: Two events are called independent if the occurrence of one event does not in any way affect the probability of the other event.
- Random Variable: A variable is called a random variable if it takes one of a specified set of values with a specified probability.



CDF, PDF, and PMF (Cont)

Given a pdf f(x): $P(x_1 < x \le x_2) = F(x_2) - F(x_1) = \int_{x_1}^{x_2} f(x) dx$

Probability Mass Function: For discrete random variables:

$$f(x_i) = p_i \qquad f(x_i)$$

$$P(x_{1} < x \le x_{2}) = F(x_{2}) - F(x_{1}) \overset{x_{i}}{=} \sum_{i} p_{i} \\ x_{1} < x_{i} \le x_{2}$$

Mean, Variance, CoV

□ Mean or Expected Value:

Mean $\mu = E(x) = \sum_{i=1}^{n} p_i x_i = \int_{-\infty}^{+\infty} x f(x) dx$

□ Variance: The expected value of the square of distance between x and its mean

$$Var(x) = \sigma^{2} = E[(x - \mu)^{2}] = \sum_{i=1}^{n} p_{i}(x_{i} - \mu)^{2}$$
$$= \int_{-\infty}^{+\infty} (x_{i} - \mu)^{2} f(x) dx$$

□ Coefficient of Variation:

C.O.V. =
$$\frac{\text{Standard Deviation}}{\text{Mean}} = \frac{\sigma}{\mu}$$

Washington University in St. Louis

Covariance and Correlation

Covariance:

$$Cov(x,y) = \sigma_{xy} = E[(x - \mu_x)(y - \mu_y)]$$

= $E(xy) - E(x)E(y)$

□ For independent variables, the covariance is zero:

$$E(xy) = E(x)E(y)$$

- Although independence always implies zero covariance, the reverse is not true.
- □ **Correlation Coefficient**: normalized value of covariance

$$Correlation(x, y) = \rho_{xy} = \frac{\sigma_{xy}^2}{\sigma_x \sigma_y}$$

The correlation always lies between -1 and +1.

Washington Univ	versity in St. Lou	is

Mean and Variance of Sums

$$\Box$$
 If x_1, x_2, \ldots, x_k


are k random variables and if a_1, a_2, \ldots, a_k are k arbitrary constants (called weights), then: $E(a_1x_1 + a_2x_2 + \cdots + a_kx_k)$ $= a_1E(x_1) + a_2E(x_2) + \cdots + a_kE(x_k)$

□ For independent variables:

$$Var(a_1x_1 + a_2x_2 + \dots + a_kx_k) = a_1^2 Var(x_1) + a_2^2 Var(x_2) + \dots + a_k^2 Var(x_k)$$

Quantiles, Median, and Mode

- □ Quantile: The *x* value at which the CDF takes a value α is called the α -quantile or 100 α -percentile. It is denoted by x_{α} : $P(x \leq x_{\alpha}) = F(x_{\alpha}) = \alpha$
- Median: The 50-percentile or (0.5-quantile) of a random variable is called its median.
- □ Mode: The most likely value, that is, x_i that has the highest probability p_i , or the *x* at which pdf is maximum, is called mode of *x*.



Normal Distribution

Normal Distribution: The sum of a large number of independent observations from any distribution has a normal distribution.

$$f(x) = \frac{1}{\sigma\sqrt{2\pi}} e^{-\frac{(x-\mu)^2}{2\sigma^2}} - \infty \le x \le +\infty$$

- \Box A normal variate is denoted at N(μ , σ).
- Unit Normal: A normal distribution with zero mean and unit variance. Also called standard normal distribution and is denoted as N(0,1).

Normal Quantiles

An α-quantile of a unit normal variate $z \sim N(0,1)$ is denoted by z_{α} . If a random variable *x* has a N(μ, σ) distribution, then $(x-\mu)/\sigma$ has a N(0,1) distribution.

$$P(\frac{x-\mu}{\sigma} \le z_{\alpha}) = \alpha$$

or

$$P(x \le \mu + z_\alpha \sigma) = \alpha$$

Washington University in St. Louis

Why Normal?

- There are two main reasons for the popularity of the normal distribution:
- 1. The sum of n independent normal variates is a normal variate. If, $(x_i \sim N(\mu_i, \sigma_i))$ then $x = \sum_{i=1}^{n} a_i x_i$ has a normal distribution with mean $\mu = \sum_{i=1}^{n} a_i \mu_i$ and variance $\sigma^2 = \sum_{i=1}^{n} a_i^2 \sigma_i^2$.
- 2. The sum of a large number of independent observations from any distribution tends to have a normal distribution. This result, which is called central limit theorem, is true for observations from all distributions

=> Experimental errors caused by many factors are normal.


Summarizing Data by a Single Number


- □ Indices of central tendencies: Mean, Median, Mode
- Sample Mean is obtained by taking the sum of all observations and dividing this sum by the number of observations in the sample.
- Sample Median is obtained by sorting the observations in an increasing order and taking the observation that is in the middle of the series. If the number of observations is even, the mean of the middle two values is used as a median.
- Sample Mode is obtained by plotting a histogram and specifying the midpoint of the bucket where the histogram peaks. For categorical variables, mode is given by the category that occurs most frequently.
- Mean and median always exist and are unique. Mode, on the other hand, may not exist.

Washington University in St. Louis

CSE567M

Mean, Median, and Mode: Relationships





Indices of Central Tendencies: Examples

- Most used resource in a system: Resources are categorical and hence mode must be used.
- Interarrival time: Total time is of interest and so mean is the proper choice.
- Load on a Computer: Median is preferable due to a highly skewed distribution.
- Average Configuration: Medians of number devices, memory sizes, number of processors are generally used to specify the configuration due to the skewness of the distribution.

Using mean of s	ignificant	lisuses of ly different val	
(10+1000)/2 = 5		d to the skown	ess of distribution.
	vstem A		-
<u></u>	$\frac{10}{10}$	<u>5 5 5 5 5 5 5 5 5 5 5 5 5 5 5 5 5 5 5 </u>	-
	9	5	
	11	5	
	10	4	
	10	31	
	5um=50	Sum=50	-
Μ	ean=10	Mean=10	
Typ	ical=10	Typical=5	
Washington University in St. Louis		CSE567M	- ©2008 Raj J
		12-18	

Misuses of Means (cont)

• Multiplying means to get the mean of a product $\nabla (f \circ h) = \int f (f \circ h) df (f \circ h) df$

 $E(xy) \neq E(x)E(y)$

 Example: On a timesharing system, Average number of users is 23 Average number of sub-processes per user is 2 What is the average number of sub-processes? Is it 46? No! The number of sub-processes a user spawns depends upon how much load there is on the system.
 Taking a mean of a article with different bases

 Taking a mean of a ratio with different bases. Already discussed in Chapter 11 on ratio games and is discussed further later

Geometric Mean

$$\dot{x} = \left(\prod_{i=1}^{n} x_i\right)^{\frac{1}{n}}$$

Geometric mean is used if the product of the observations is a quantity of interest.

Geometric Mean: Example The performance improvements in 7 layers: Performance Protocol Layer Improvement 18%7 13%6 11%58%4 3 10%28%25%Average improvement per layer $= \{(1.18)(1.13)(1.11)(1.08)(1.10)(1.28)(1.05)\}^{\frac{1}{7}} - 1$ = 0.13Washington University in St. Louis CSE567M ©2008 Raj Jain 12 - 21


Examples of Multiplicative Metrics

- □ Cache hit ratios over several levels of caches
- Cache miss ratios
- Percentage performance improvement between successive versions
- Average error rate per hop on a multi-hop path in a network.

Geometric Mean of Ratios

$$gm(\frac{x_1}{y_1}, \frac{x_2}{y_2}, \dots, \frac{x_n}{y_n}) = \frac{gm(x_1, x_2, \dots, x_n)}{gm(y_1, y_2, \dots, y_n)} = \frac{\frac{1}{gm(\frac{y_1}{x_1}, \frac{y_2}{x_2}, \dots, \frac{y_n}{x_n})}$$

- The geometric mean of a ratio is the ratio of the geometric means of the numerator and denominator
 => the choice of the base does not change the conclusion.
- It is because of this property that sometimes geometric mean is recommended for ratios.
- However, if the geometric mean of the numerator or denominator do not have any physical meaning, the geometric mean of their ratio is meaningless as well.



- □ Used whenever an arithmetic mean can be justified for $1/x_i$ E.g., Elapsed time of a benchmark on a processor
- □ In the *i*th repetition, the benchmark takes t_i seconds. Now suppose the benchmark has *m* million instructions, MIPS x_i computed from the *i*th repetition is: $x_i = \frac{m}{t_i}$

*t*_i's should be summarized using arithmetic mean since the sum of t_i has a physical meaning
 => *x*_i's should be summarized using harmonic mean since the sum of 1/*x*_i's has a physical meaning.

©2008 Raj Jain

Harmonic Mean (Cont)

□ The average MIPS rate for the processor is:

$$\ddot{x} = \frac{n}{\frac{1}{m/t_1} + \frac{1}{m/t_2} + \dots + \frac{1}{m/t_n}}$$
$$= \frac{m}{\frac{1}{n}(t_1 + t_2 + \dots + t_n)}$$

- □ However, if x_i 's represent the MIPS rate for *n* different benchmarks so that *i*th benchmark has m_i million instructions, then harmonic mean of *n* ratios m_i/t_i cannot be used since the sum of the t_i/m_i does not have any physical meaning.
- □ Instead, as shown later, the quantity $\sum m_i / \sum t_i$ is a preferred average MIPS rate.

Weighted Harmonic Mean

The weighted harmonic mean is defined as follows: $\ddot{x} = \frac{1}{\frac{w_1}{x_1} + \frac{w_2}{x_2} + \dots + \frac{w_n}{x_n}}$ where, w_i 's are weights which add up to one: $w_1 + w_2 + \dots + w_n = 1$ All weights equal => Harmonic, I.e., $w_i = 1/n$. In case of MIPS rate, if the weights are proportional to the size of the benchmark: $w_i = \frac{m_i}{m_1 + m_2 + \dots + m_n}$ Weighted harmonic mean would be:

$$\ddot{x} = \frac{m_1 + m_2 + \dots + m_n}{t_1 + t_2 + \dots + t_n}$$

Mean of A Ratio


1. If the sum of numerators and the sum of denominators, both have a physical meaning, the average of the ratio is the ratio of the averages.

For example, if $x_i = a_i/b_i$, the average ratio is given by:

$$Average\left(\frac{a_1}{b_1}, \frac{a_2}{b_2}, \cdots, \frac{a_n}{b_n}\right) = \frac{a_1 + a_2 + \cdots + a_n}{b_1 + b_2 + \cdots + b_n}$$
$$= \frac{\sum_{i=1}^n a_i}{\sum_{i=1}^n b_i}$$
$$= \frac{\frac{1}{n} \sum_{i=1}^n a_i}{\frac{1}{n} \sum_{i=1}^n b_i} = \frac{\overline{a}}{\overline{b}}$$
$$Washington University in St. Louis CSE567M (2008 Raj Jain)$$

Mean of a Ratio: Example						
CPU utilization						
Measurement	CPU	-				
Duration	Busy					
1	45%	-				
1	45%					
1	45%					
1	45%					
100	20%					
Sum	200	-				
Mean	$\neq 200/5$ or 40%	_				
Washington University in St. Louis	CSE567M 12-28	©2008 Raj Jain				

Example (Cont)



- □ Ratios cannot always be summarized by a geometric mean.
- □ A geometric mean of utilizations is useless.

Mean of a Ratio: Special Cases

a. If the denominator is a constant and the sum of numerator has a physical meaning, the arithmetic mean of the ratios can be used.

That is, if $b_i = b$ for all *i*'s, then:

Average
$$\left(\frac{a_1}{b}, \frac{a_2}{b}, \cdots, \frac{a_n}{b}\right)$$

= $\frac{1}{n} \left(\frac{a_1}{b} + \frac{a_2}{b} + \cdots + \frac{a_n}{b}\right)$
= $\frac{\sum_{i=1}^n a_i}{nb}$

Example: mean resource utilization.

Mean of Ratio (Cont)

b. If the sum of the denominators has a physical meaning and the numerators are constant then a harmonic mean of the ratio should be used to summarize them.

That is, if $a_i = a$ for all *i*'s, then:

Average
$$\left(\frac{a}{b_1}, \frac{a}{b_2}, \cdots, \frac{a}{b_n}\right) = \frac{n}{\frac{b_1}{a} + \frac{b_2}{a} + \cdots + \frac{b_n}{a}}$$
$$= \frac{na}{\sum_{i=1}^n b_i}$$

Example: MIPS using the same benchmark

Mean of Ratios (Cont)

2. If the numerator and the denominator are expected to follow a multiplicative property such that $a_i=c b_i$, where c is approximately a constant that is being estimated, then c can be estimated by the geometric mean of a_i/b_i .

• Example: Program Optimizer: $a_i = cb_i$

■ Where, b_i and a_i are the sizes before and after the program optimization and *c* is the effect of the optimization which is expected to be independent of the code size.

$$\log c = (\log b_i - \log a_i)$$
$$\log a_i = \log c + \log b_i$$

$$\log c = \text{arithmetic mean of} (\log b_i - \log a)$$

=> c geometric mean of b_i/a_i

or


Program Optimizer Static Size Data

		Code		
	Program	Before	After	Ratio
	BubbleP	119	89	0.75
	IntmmP	158	134	0.85
	PermP	142	121	0.85
	PuzzleP	8612	7579	0.88
	QueenP	7133	7062	0.99
	QuickP	184	112	0.61
	SieveP	2908	2879	0.99
	TowersP	433	307	0.71
	Geometric		0.79	
Things	sity in St. Louis	CSE567M		
Univers	sity in St. Louis	CSE30/M		

Washington

Summarizing Variability

"Then there is the man who drowned crossing a stream with an average depth of six inches."
 W. I. E. Gates



Indices of Dispersion

- 1. Range: Minimum and maximum of the values observed
- 2. Variance or standard deviation
- 3. 10- and 90- percentiles
- 4. Semi inter-quantile range
- 5. Mean absolute deviation

Range

- $\square Range = Max-Min$
- □ Larger range => higher variability
- □ In most cases, range is not very useful.
- □ The minimum often comes out to be zero and the maximum comes out to be an ``outlier'' far from typical values.
- Unless the variable is bounded, the maximum goes on increasing with the number of observations, the minimum goes on decreasing with the number of observations, and there is no ``stable" point that gives a good indication of the actual range.
- Range is useful if, and only if, there is a reason to believe that the variable is bounded.

Variance

$$s^{2} = \frac{1}{n-1} \sum_{i=1}^{n} (x_{i} - \bar{x})^{2}$$

where $\bar{x} = \frac{1}{n} \sum_{i=1}^{n} x_{i}$

- □ The divisor for s^2 is n-1 and not n.
- □ This is because only *n*-1 of the *n* differences $(x_i \bar{x})$ are independent.
- □ Given *n*-1 differences, *n*th difference can be computed since the sum of all *n* differences must be zero.
- □ The number of independent terms in a sum is also called its **degrees of freedom**.

Variance (Cont)

□ Variance is expressed in units which are square of the units of the observations.

=> It is preferable to use standard deviation.

Ratio of standard deviation to the mean, or the coefficient of variation (COV), is even better because it takes the scale of measurement (unit of measurement) out of variability consideration.

Percentiles

- □ Specifying the 5-percentile and the 95-percentile of a variable has the same impact as specifying its minimum and maximum.
- It can be done for any variable, even for variables without bounds.
- When expressed as a fraction between 0 and 1 (instead of a percent), the percentiles are also called quantiles.
 => 0.9-quantile is the same as 90-percentile.
- □ **Fractile**= quantile.
- The percentiles at multiples of 10% are called deciles. Thus, the first decile is 10-percentile, the second decile is 20-percentile, and so on.

Quartiles

□ **Quartiles** divide the data into four parts at 25%, 50%, and 75%.

=> 25% of the observations are less than or equal to the first quartile Q_1 ,

50% of the observations are less than or equal to the second quartile Q_2 , and

75% are less than the third quartile Q_3 .

□ Notice that the second quartile Q_2 is also the median.

- The α-quantiles can be estimated by sorting the observations and taking the [(n-1)α+1]th element in the ordered set. Here, [.] is used to denote rounding to the nearest integer.
- □ For quantities exactly half way between two integers use the lower integer.

Semi Inter-Quartile Range

- $\Box \text{ Inter-quartile range} = Q_3 Q_1$
- □ Semi inter-quartile range (SIQR)

$$SIQR = \frac{Q_3 - Q_1}{2} = \frac{x_{0.75} - x_{0.25}}{2}$$

Mean Absolute Deviation

Mean absolute deviation = $\frac{1}{n} \sum_{i=1}^{n} |x_i - \bar{x}|$

□ No multiplication or square root is required

Comparison of Variation Measures

- □ Range is affected considerably by outliers.
- Sample variance is also affected by outliers but the affect is less
- □ Mean absolute deviation is next in resistance to outliers.
- Semi inter-quantile range is very resistant to outliers.
- □ If the distribution is highly skewed, outliers are highly likely and SIQR is preferred over standard deviation
- □ In general, SIQR is used as an index of dispersion whenever median is used as an index of central tendency.
- For qualitative (categorical) data, the dispersion can be specified by giving the number of most frequent categories that comprise the given percentile, for instance, top 90%.


Measures of Variation: Example

- In an experiment, which was repeated 32 times, the measured CPU time was found to be {3.1, 4.2, 2.8, 5.1, 2.8, 4.4, 5.6, 3.9, 3.9, 2.7, 4.1, 3.6, 3.1, 4.5, 3.8, 2.9, 3.4, 3.3, 2.8, 4.5, 4.9, 5.3, 1.9, 3.7, 3.2, 4.1, 5.1, 3.2, 3.9, 4.8, 5.9, 4.2}.
- The sorted set is {1.9, 2.7, 2.8, 2.8, 2.8, 2.9, 3.1, 3.1, 3.2, 3.2, 3.3, 3.4, 3.6, 3.7, 3.8, 3.9, 3.9, 3.9, 4.1, 4.1, 4.2, 4.2, 4.4, 4.5, 4.5, 4.8, 4.9, 5.1, 5.1, 5.3, 5.6, 5.9}.
- □ 10-percentile = [1+(31)(0.10) = 4th element = 2.8
- 90-percentile = [1+(31)(0.90)] = 29th element = 5.1
- □ First quartile $Q_1 = [1+(31)(0.25)] = 9$ th element = 3.2
- Median $Q_2 = [1+(31)(0.50)] = 16$ th element = 3.9

□ Third quartile
$$Q_1 = [1+(31)(0.75)] = 24$$
th element = 4.5

$$SIQR = \frac{Q_3 - Q_1}{2} = \frac{4.5 - 3.2}{2} = 0.65$$

Washington University in St. Louis



Selecting the Index of Dispersion (Cont)

- □ The decision rules given above are not hard and fast.
- Network designed for average traffic is grossly under-designed.
 The network load is highly skewed

=> Networks are designed to carry 95 to 99-percentile of the observed load levels

- =>Dispersion of the load should be specified via range or percentiles.
- Power supplies are similarly designed to sustain peak demand rather than average demand.
- □ Finding a percentile requires several passes through the data, and therefore, the observations have to be stored.
- Heuristic algorithms, e.g., P² allows dynamic calculation of percentiles as the observations are generated.

See Box 12.1 in the book for a summary of formulas for various indices of central tendencies and dispersion Washington University in St. Louis

Determining Distribution of Data

- The simplest way to determine the distribution is to plot a histogram
- □ Count observations that fall into each cell or bucket
- □ The key problem is determining the cell size.
- Small cells =>large variation in the number of observations per cell
- □ Large cells => details of the distribution are completely lost.
- It is possible to reach very different conclusions about the distribution shape
- One guideline: if any cell has less than five observations, the cell size should be increased or a variable cell histogram should be used.

Quantile-Quantile plots

- □ $y_{(i)}$ is the observed q_i th quantile x_i = theoretical q_i th quantile
- \Box (x_i , $y_{(i)}$) plot should be a straight line

 $x_i = F^{-1}(q_i)$

□ To determine the q_i th quantile x_i , need to invert the cumulative distribution function.

$$q_i = F(x_i)$$

• or

Table 28.1 lists the inverse of CDF for a number of distributions.

Quantile-Quantile plots (Cont)

□ Approximation for normal distribution N(0,1)


$$x_i = 4.91[q_i^{0.14} - (1 - q_i)^{0.14}]$$

□ For $N(\mu, \sigma)$, the x_i values computed above are scaled to $\mu+\sigma x_i$ before plotting.

Quantile-Quantile Plots: Example

The difference between the values measured on a system and those predicted by a model is called modeling error. The modeling error for eight predictions of a model were found to be -0.04, -0.19, 0.14, -0.09, -0.14, 0.19, 0.04, and 0.09.

	i	$q_i = \frac{i - 0.5}{n}$	y_i	x_i					
	1	0.0625	-0.19	-1.535					
	2	0.1875	-0.14	-0.885					
	3	0.3125	-0.09	-0.487					
	4	0.4375	-0.04	-0.157					
	5	0.5625	0.04	0.157					
	6	0.6875	0.09	0.487					
	7	0.8125	0.14	0.885					
	8	0.9375	0.19	1.535					
Washington University in St. Louis		CS							
12-50									



Interpretation of Quantile-Quantile Data (a) Long Taile (a) Normal Observed Oberned quandles quantiles Normal quantiles Normal guantiles (d) Asymmetric (c) Short tails Observed Observed g marrilles g man (Bes Normal quantiles Normal or suffice Washington University in St. Louis CSE567M ©2008 Raj Jain 12-52



- Sum of a large number of random variates is normally distributed.
- Indices of Central Tendencies: Mean, Median, Mode, Arithmetic, Geometric, Harmonic means
- Indices of Dispersion: Range, Variance, percentiles, Quartiles, SIQR
- Determining Distribution of Data: Quantile-Quantile plots

Homework

- □ Read chapter 12
- □ Submit answers to Exercises 12.7 and 12.15

Exercise 12.7

- The execution times of queries on a database is normally distributed with a mean of 5 seconds and a standard deviation of 1 second. Determine the following:
 - a. What is the probability of the execution time being more than 8 seconds.
 - b. What is the probability of the execution time being less than 6 seconds.
 - c. What percent of responses will take between 4 and 7 seconds?
 - d. What is the 95-percentile execution time?

Exercise 12.15

Plot a normal quantile-quantile plot for the following sample of errors:

-0.04444	-0.04439	-0.04165	-0.03268	-0.03235	-0.03182	-0.02771	-0.02650
-0.02569	-0.02358	-0.02330	-0.02305	-0.02213	-0.02128	-0.01793	-0.01668
-0.01565	-0.01509	-0.01432	-0.00978	-0.00889	-0.00687	-0.00543	-0.00084
-0.00083	-0.00048	-0.00024	0.00079	0.00082	0.00106	0.00110	0.00132
0.00162	0.00181	0.00280	0.00379	0.00411	0.00424	0.00553	0.00865
0.01026	0.01085	0.01440	0.01562	0.01975	0.01996	0.02016	0.02078
0.02134	0.02252	0.02414	0.02568	0.02682	0.02855	0.02889	0.03072
0.03259	0.03754	0.04263	0.04276				

□ Are the errors normally distributed?