





- □ ATM vs Phone Networks and Data Networks
- □ ATM Protocol Layers
- □ Cell Header Format, AALs
- Physical Media

The Ohio State University

ATM

- Asynchronous Transfer Mode
- □ ATM Net = Data Net + Phone Net
- Combination of Internet method of communication (packet switching) and phone companies' method (circuit switching)





- Current phone networks are synchronous (periodic).
 ATM = Asynchronous Transfer Mode
- Phone networks use circuit switching. ATM networks use "Packet" Switching
- In phone networks, all rates are multiple of 8 kbps.
 With ATM service, you can get any rate.
 You can vary your rate with time.
- With current phone networks, all high speed circuits are manually setup. ATM allows dialing any speed Jain The Ohio State University

ATM vs Data Networks


- Signaling: Internet Protocol (IP) is connectionless.
 You cannot reserve bandwidth in advance.
 ATM is connection-oriented.
 You declare your needs before using the network.
- □ PNNI: Path based on quality of service (QoS)
- Switching: In IP, each packet is addressed and processed individually.
- Traffic Management: Loss based in IP.
 ATM has 1996 traffic management technology.
 Required for high-speed and variable demands.

Cells: Fixed size or small size is not important



New needs:
 Solution 1: Fix the old house (cheaper initially)
 Solution 2: Buy a new house (pays off over a long run)


The Ohio State University



ATM Interfaces

- User to Network Interface (UNI): Public UNI, Private UNI
- □ Network to Node Interface (NNI):
 - Private NNI (P-NNI)
 - Public NNI =Inter-Switching System Interface (ISSI) Intra-LATA ISSI (Regional Bell Operating Co)
 - > Inter-LATA ISSI (Inter-exchange Carriers)
 ⇒ Broadband Inter-Carrier Interface (B-ICI)
- Data Exchange Interface (DXI)
 Between routers and ATM Digital Service Units (DSU)

Protocol Layers



Protocol Layers

- □ The ATM Adaptation Layer
 - How to break messages to cells
- **The ATM Layer**
 - o Transmission/Switching/Reception
 - Congestion Control/Buffer management
 - Cell header generation/removal at source/destination
 - Cell address translation
 - Sequential delivery


Virtual Circuit Switching 2 Circuit Switching: bits coming on wire 4 go on wire 2 Virtual Circuit Switching: Cells coming on VCI=4 go on VCI=2

Cell Header Format

□ GFC = Generic Flow Control


• (Was used in UNI but not in NNI)

□ VPI/VCI = $0/0 \Rightarrow$ Idle cell; $0/n \Rightarrow$ Signaling



Header Error Check (HEC)

- **1** $+ x + x^2 + x^8$
- Protects header only
- Optional Correction mode: Correct one bit errors if no earlier errors
- Discard cells with bad HEC
- □ Recalculated on each hop



Payload Type Field Coding


- \bigcirc 000User data cell, no congestion, AAU = 0
- \Box 001 User data cell, no congestion, AAU = 1
- \Box 010User data cell, congestion, AAU = 0
- \Box 011User data cell, congestion, AAU = 1
- □ 100 Segment Operation and management (OAM) cell
- □ 101 End-to-end OAM cell
- □ 110Resource management cell
- □ 111Reserved
- ATM-user-to-ATM-user (AAU) bit available for userto-user indication


The Ohio State University

Path vs Channels

24/28-bit connection identifier
 First 8/12 bits: Virtual Path,
 Last 16 bits: Virtual Circuit

□ VP service allows new VC's w/o orders to carriers






Original Classes of Traffic


	Class A	Class B	Class C	Class D
Time Sync	Yes	Yes	No	No
Bit Rate	Constant	Variable	Variable	Variable
Connection	Yes	Yes	Yes	No
-Oriented				
Examples	Circuit	Comp.	Frame	SMDS
	Emulation	Video	Relay	
AAL	AAL1	AAL2	AAL3	AAL4


The Ohio State University



AAL2

- □ Ideal for low bit rate voice
- □ Variable/constant rate voice
- □ Multiple users per VC
- Compression and Silence suppression
- □ Idle channel suppression






SONET

- Synchronous optical network
- Standard for digital optical transmission (bit pipe)
- Developed originally by Bellcore.
 Standardized by ANSI T1X1
 Standardized by CCITT

 \Rightarrow Synchronous Digital Hierarchy (SDH)

□ You can lease a SONET connection from carriers





Signal Hierarchy

Synchronous Transport Signal Level $n = STS - n = n \times 51.84$ Mbps STM=Synchronous Transport Module, OC=Optical Carrier level

ANSI	Optical	CCITT	Data Rate	Payload Rate
Designation	Signal	Designation	(Mbps)	(Mbps)
STS-1	OC-1		51.84	50.112
STS-3	OC-3	STM-1	155.52	150.336
STS-9	OC-9	STM-3	466.56	451.008
STS-12	OC-12	STM-4	622.08	601.344
STS-18	OC-18	STM-6	933.12	902.016
STS-24	OC-24	STM-8	1244.16	1202.688
STS-36	OC-36	STM-12	1866.24	1804.032
STS-48	OC-48	STM-16	2488.32	2405.376
STS-96	OC-96	STM-32	4976.64	4810.176
STS-192	OC-192	STM-64	9953.28	9620.928

The Ohio State University





SONET STS-3c

- \Box Payload rate = 9 \times 260 \times 8/125 = 149.76 Mbps
- □ Cell payload rate = 135.63 Mbps
- □ Cell delineation using HEC.
 - Look for 5-byte blocks with HEC separated by 48 bytes
- Cells are packed one after another ⇒ One can send 127 bits matching the scrambling sequence resulting in all 1's or 0's.
 - Scramble by dividing by $1 + x^{43}$.

Only one in 2^{43} patterns will cause all 1's or 0's.

Physical Media


- Multimode Fiber: 100 Mbps using 4b/5b,
 155 Mbps SONET STS-3c, 155 Mbps 8b/10b
- □ Single-mode Fiber: 155 Mbps STS-3c, 622 Mbps
- Plastic Optical Fiber: 155 Mbps
- □ Shielded Twisted Pair (STP): 155 Mbps 8b/10b
- Coax: 45 Mbps, DS3, 155 Mbps
- □ Unshielded Twisted Pair (UTP)

• UTP-3 (phone wire) at 25.6, 51.84, 155 Mbps

• UTP-5 (Data grade UTP) at 155 Mbps

□ DS1, DS3, STS-3c, STM-1, E1, E3, J2, n × T1

The Ohio State University



- Protocol Layers: AAL, ATM, Physical layers, Cell format
- □ Interfaces: PNNI, NNI, B-ICI, DXI

Homework

- □ Read Sections 11.1-11.5 of Stallings
- □ Submit answers to Exercise 11.4

The Ohio State University